

Cómo configurar SSO con Microsoft AD FS

- [Requisitos del sistema](#)
- [Paso 1. Verificar ajustes de AD FS](#)
- [Paso 2. iSpring LMS Ajustes](#)
- [Paso 3. Configuración de la parte confiable de AD FS](#)
- [Paso 4. Creando reglas de reclamaciones](#)
- [Paso 5. Ajustando los Ajustes de Confianza](#)
- [Paso 6. Punto final Ajustes](#)
- [Paso 7. Verificar inicio de sesión único \(SSO\)](#)
- [Correlación de campos de iSpring LMS y SSO](#)
- [Autorización sin SAML](#)


Requisitos del sistema

- Un servidor con Microsoft Server 2019/ 2016/ 2012 R2 en ejecución
- AD FS 5.0/4.0/3.0 instalado en su servidor
- Un certificado SSL para firmar su página de usuario de AD FS y la huella digital de ese certificado
- Una cuenta de iSpring LMS
- Un usuario de LMS con el rol *Titular de la cuenta* o *Administrador de la cuenta*


Esta guía cubre la configuración de SSO SAML mediante AD FS 4.0 en Windows Server.

Paso 1. Verificar ajustes de AD FS

1. Inicie sesión en su servidor AD FS y abra la consola de administración de ADFS mediante el acceso directo en **Control Panel** (Panel de control) > **System and Security** (Sistema y seguridad) > **Administrative Tools** (Herramientas administrativas).




2. Haga clic derecho en **Service** (Servicio) y seleccione **Edit Federation Service Properties** (Editar propiedades del servicio de federación).



3. Verifique que los ajustes **General** (Generales) coincidan con sus entradas DNS y nombres de certificado. Tome nota del **Federation Service Identifier** (Identificador del servicio de federación), ya que se usa en los ajustes de configuración SAML 2.0 de iSpring LMS.

4. En el campo de nombre **Federation Service** (Servicio de federación), utilice un dominio de tercer nivel, por ejemplo, adfs.ispring.com.




The image shows a Windows-style dialog box titled "Federation Service Properties" with a close button (X) in the top right corner. It has three tabs: "General", "Organization", and "Events". The "General" tab is selected. The dialog contains the following fields and controls:

- Federation Service display name:** A text box containing "iSpring Federation Service". Below it is an example: "Example: Fabrikam Federation Service".
- Federation Service name:** A text box containing "adfs.ispring.com". Below it is an example: "Example: fs.fabrikam.com".
- Federation Service identifier:** A text box containing "http://adfs.ispring.com/adfs/services/trust". Below it is an example: "Example: http://fs.fabrikam.com/adfs/services/trust".
- Web SSO lifetime (minutes):** A spinner box set to "480".
- ☐ **Enable delegation for service administration**
 - Delegate name:** An empty text box.
 - Edit...** button.
- ☒ **Allow Local System account for service administration**
- ☒ **Allow Local Administrators group for service administration**

At the bottom of the dialog are three buttons: "OK", "Cancel", and "Apply".

Paso 2. iSpring LMS Ajustes

1. Examine los certificados.
2. Haga clic con el botón derecho en el certificado y seleccione **View Certificate** (Ver certificado).
3. Ir a la pestaña **Details** (Detalles).
4. Encuentra el campo **Thumbprint** (Huella Digital) y copia el contenido.



5. Inicie sesión en su cuenta de iSpring LMS. Luego, vaya a **Servicios Ajustes SSO** y haga clic en **SAML**.



6. Inserte su **Thumbprint** (huella digital) en el campo **Huella digital del certificado** y elimine todos los espacios entre los caracteres.
7. En iSpring LMS, en la página de **ajustes de integración SSO**, rellene estos campos:

Nombre del campo	Ejemplo
URL del emisor (ID de entidad del IdP)	http://YOUR_ADFS_SERVERNAME/adfs/services/trust
URL de inicio de sesión único	https://YOUR_ADFS_SERVERNAME/adfs/ls/idpinitiatedsignon.aspx
URL de cierre de sesión	https://YOUR_ADFS_SERVERNAME/adfs/ls/?wa=wsignout1.0

Los parámetros de la URL de inicio de sesión único y la URL de cierre de sesión pueden diferir, según el AD FS.

← Integración de Inicio de sesión único (SSO)

Ajustes SSO

Accesos directos

SAML

JWT

OpenID

¿Qué es esto?

Activar

Ajustes de conexión

URL del emisor (ID de identidad del IdP):

https://YOUR_ADFS_SERVERNAME/adfs/services/trust

URL de inicio de sesión único:

https://YOUR_ADFS_SERVERNAME/adfs/ls/idpinitiatedsignon.aspx

URL de cierre de sesión:

https://YOUR_ADFS_SERVERNAME/adfs/ls/?wa=wsignout1.0

Huella digital del certificado:

ab123456789abcdefg123456789a1a

☒ Redirigir a los usuarios a la página de inicio de sesión SSO

URL del emisor (ID de entidad del IdP)	La URL que identifica de forma única el servicio del proveedor de identidad. Este valor es igual al elemento E misor de la solicitud SAML enviada por el proveedor de identidad.
URL de inicio de sesión único	Es la ruta al script del servidor que genera solicitudes de confirmación de identificador SAML para gestionar la autorización.
URL de cierre de sesión	Es la ruta al script del servidor que genera solicitudes de confirmación de identificador SAML para gestionar el cierre de sesión.
Huella digital del certificado	Esta es una versión abreviada del certificado de clave pública para verificar una firma digital. Se utiliza para confirmar solicitudes de firma emitidas por un proveedor de identidad. Saber más sobre las huellas digitales de certificados aquí .
Redirigir a los usuarios a la página de inicio de sesión SSO	Si esta opción está habilitada, la página de usuario de iSpring tendrá la siguiente URL: https://yourcompany.ispringlearn.com/sso/login .

8. Haga clic en **Activar**.
9. Luego, [añada el enlace](#) al sitio corporativo en la sección **Accesos directos**.

← Integración de Inicio de sesión único (SSO)

Ajustes SSO

Accesos directos


Los accesos directos están ahora en la sección Ajustes

Puede añadir nuevos enlaces a sitios y servicios usados frecuentemente en Ajustes > Opciones adicionales > Accesos directos.


Ir a accesos directos

Paso 3. Configuración de la parte confiable de AD FS

1. Vaya a la consola de administración de AD FS y seleccione **Relying Party Trusts** (Confianzas de partes confiables), haga clic con el botón derecho sobre ella y seleccione **Add Relying Party Trust** (Añadir confianza de parte confiable).



2. Seleccione **Claims aware** (Consciente de las reclamaciones) y haga clic en **Start** (Iniciar).



3. En la **Select Data Source** (Seleccionar origen de datos) fase, seleccione la última opción: **Enter data about the relying party manually** (Introducir datos sobre la parte confiable manualmente).

Add Relying Party Trust Wizard

Select Data Source

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Select an option that this wizard will use to obtain data about this relying party:

☐ Import data about the relying party published online or on a local network

Use this option to import the necessary data and certificates from a relying party organization that publishes its federation metadata online or on a local network.

Federation metadata address (host name or URL):

Example: fs.contoso.com or https://www.contoso.com/app

☐ Import data about the relying party from a file

Use this option to import the necessary data and certificates from a relying party organization that has exported its federation metadata to a file. Ensure that this file is from a trusted source. This wizard will not validate the source of the file.

Federation metadata file location:

☒ Enter data about the relying party manually

Use this option to manually input the necessary data about this relying party organization.

< Previous **Next >** Cancel

4. En la siguiente pantalla, introduzca un **Display name** (Nombre para mostrar) que pueda reconocer en el futuro. Haga clic en **Next** (Siguiente).

Add Relying Party Trust Wizard

Specify Display Name

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Enter the display name and any optional notes for this relying party.

Display name:

Notes:

< Previous **Next >** Cancel

5. En la etapa **Configure Certificate** (Configurar certificado), deje los valores Predeterminadas. Haga clic en **Next** (Siguiente).

Add Relying Party Trust Wizard

Configure Certificate

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Specify an optional token encryption certificate. The token encryption certificate is used to encrypt the claims that are sent to this relying party. The relying party will use the private key of this certificate to decrypt the claims that are sent to it. To specify the certificate, click Browse.

Issuer:
Subject:
Effective date:
Expiration date:

View... Browse... Remove

< Previous Next > Cancel

6. En la siguiente pantalla, marque la casilla **Enable support for the SAML 2.0 WebSSO protocol** (Habilitar soporte para el protocolo WebSSO SAML 2.0). La URL del servicio será: <https://youraccount.ispringlearn.com/module.php/saml/sp/saml2-acps.php/default-sp>.

Add Relying Party Trust Wizard

Configure URL

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers
- Choose Access Control Policy
- Ready to Add Trust
- Finish

AD FS supports the WS-Trust, WS-Federation and SAML 2.0 WebSSO protocols for relying parties. If WS-Federation, SAML, or both are used by the relying party, select the check boxes for them and specify the URLs to use. Support for the WS-Trust protocol is always enabled for a relying party.

☐ Enable support for the WS-Federation Passive protocol

The WS-Federation Passive protocol URL supports Web-browser-based claims providers using the WS-Federation Passive protocol.

Relying party WS-Federation Passive protocol URL:

Example: <https://fs.contoso.com/adfs/ls/>

☒ Enable support for the SAML 2.0 WebSSO protocol

The SAML 2.0 single-sign-on (SSO) service URL supports Web-browser-based claims providers using the SAML 2.0 WebSSO protocol.

Relying party SAML 2.0 SSO service URL:

<https://youraccount.ispringlearn.com/module.php/saml/sp/saml2-acps.php/default-sp>

Example: <https://www.contoso.com/adfs/ls/>

< Previous Next > Cancel

7. En la etapa **Configure Identifiers** (Configurar identificadores), añada el **Relying party trust identifier** (Identificador de confianza de parte confiable) como <https://youraccount.ispringlearn.com/module.php/saml/sp/metadata.php/default-sp>. Haga clic en **Add** (Añadir).

Add Relying Party Trust Wizard

Configure Identifiers

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers**
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Relying parties may be identified by one or more unique identifier strings. Specify the identifiers for this relying party trust.

Relying party trust identifier:

Example: https://fs.contoso.com/adfs/services/trust

Relying party trust identifiers:

Remove

< Previous Next > Cancel

8. Luego, haga clic en **Next** (Siguiente).

Add Relying Party Trust Wizard

Configure Identifiers

Steps

- Welcome
- Select Data Source
- Specify Display Name
- Configure Certificate
- Configure URL
- Configure Identifiers**
- Choose Access Control Policy
- Ready to Add Trust
- Finish

Relying parties may be identified by one or more unique identifier strings. Specify the identifiers for this relying party trust.

Relying party trust identifier:

Example: https://fs.contoso.com/adfs/services/trust


Relying party trust identifiers:

https://youraccount.ispringlearn.com/module.php/saml/sp/metadata.php/default-sp


Remove

< Previous **Next >** Cancel


9. En el siguiente paso, elija **Permit everyone** (Permitir a todos). Haga clic en **Next** (Siguiente).



10. En la etapa **Ready to Add Trust** (Listo para Añadir Confianza), deje los valores Predeterminadas. Haga clic en **Next** (Siguiente).




11. En el último paso, marque la casilla **Configure claims issuance policy for this application** (Configurar la directiva de emisión de reclamaciones para esta aplicación). Luego, haga clic en **Close** (Cerrar).



Paso 4. Creando reglas de reclamaciones

1. Abra el panel de control de AD FS. En la sección de **Relying Party Trusts** (Confianzas de la Parte Dependiente), haga clic derecho en el nombre y haga clic en **Edit Claim Issuance Policy** (Editar Política de Emisión de Reclamaciones).



2. Añada la primera regla. Para hacer esto, haga clic en **Add Rule...** (Añadir regla...).

Edit Claim Issuance Policy for iSpring Learn SSO

Issuance Transform Rules

The following transform rules specify the claims that will be sent to the relying party.

Order	Rule Name	Issued Claims
-------	-----------	---------------

↑

↓

Add Rule... Edit Rule... Remove Rule...

OK Cancel Apply

3. Seleccione **Send LDAP Attributes as Claims** (Enviar atributos LDAP como reclamaciones). Haga clic en **Next** (Siguiente).

Add Transform Claim Rule Wizard

Select Rule Template

Steps

- Choose Rule Type
- Configure Claim Rule

Select the template for the claim rule that you want to create from the following list. The description provides details about each claim rule template.

Claim rule template:

- Send LDAP Attributes as Claims
- Send LDAP Attributes as Claims
- Send Group Membership as a Claim
- Transform an Incoming Claim
- Pass Through or Filter an Incoming Claim
- Send Claims Using a Custom Rule

multiple claims from a single rule using this rule type. For example, you can use this rule template to create a rule that will extract attribute values for authenticated users from the displayName and telephoneNumber Active Directory attributes and then send those values as two different outgoing claims. This rule may also be used to send all of the user's group memberships. If you want to only send individual group memberships, use the Send Group Membership as a Claim rule template.

< Previous Next > Cancel

4. En el paso **Configure Claim Rule** (Configurar regla de reclamación), en el campo Nombre de la regla de reclamación, introduzca un nombre para la regla, por ejemplo, **Attributes of iSpring LMS** (Atributos de iSpring LMS).

Add Transform Claim Rule Wizard

Configure Rule

Steps

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to send the values of LDAP attributes as claims. Select an attribute store from which to extract LDAP attributes. Specify how the attributes will map to the outgoing claim types that will be issued from the rule.

Claim rule name:

Attributes to iSpring Learn

Rule template: Send LDAP Attributes as Claims

Attribute store:

Active Directory

Mapping of LDAP attributes to outgoing claim types:

	LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
▶	E-Mail-Addresses	email
*		

< Previous Finish Cancel

5. Elija **Active Directory** como su almacén de atributos.

Add Transform Claim Rule Wizard

Configure Rule

Steps

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to send the values of LDAP attributes as claims. Select an attribute store from which to extract LDAP attributes. Specify how the attributes will map to the outgoing claim types that will be issued from the rule.

Claim rule name:

Rule template: Send LDAP Attributes as Claims

Attribute store:

Mapping of LDAP attributes to outgoing claim types:

	LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
▶	E-Mail-Addresses	email
*		

< Previous **Finish** Cancel

6. A continuación, seleccione estos valores:

- En la columna **LDAP Attribute** (Atributo LDAP), establezca E-Mail-Addresses.
- En la columna **Outgoing Claim Type** (Tipo de reclamación saliente), establezca el valor de correo electrónico, como en iSpring LMS <https://youraccount.ispringlearn.com/settings/sso>.

Add Transform Claim Rule Wizard

Configure Rule

Steps

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to send the values of LDAP attributes as claims. Select an attribute store from which to extract LDAP attributes. Specify how the attributes will map to the outgoing claim types that will be issued from the rule.

Claim rule name:

Rule template: Send LDAP Attributes as Claims

Attribute store:

Mapping of LDAP attributes to outgoing claim types:

	LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
▶	E-Mail-Addresses	email
*		

< Previous **Finish** Cancel

7. Haga clic en **Finish** (Finalizar) para guardar la nueva regla.

Add Transform Claim Rule Wizard

Configure Rule

Steps

- Choose Rule Type
- Configure Claim Rule

You can configure this rule to send the values of LDAP attributes as claims. Select an attribute store from which to extract LDAP attributes. Specify how the attributes will map to the outgoing claim types that will be issued from the rule.

Claim rule name:

Rule template: Send LDAP Attributes as Claims

Attribute store:

Mapping of LDAP attributes to outgoing claim types:

	LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
▶	E-Mail-Addresses	email
•		

< Previous **Finish** Cancel

8. Luego, añada la segunda regla y seleccione **Transform an Incoming Claim** (Transformar una reclamación entrante) como plantilla.

Add Transform Claim Rule Wizard

Select Rule Template

Steps

- Choose Rule Type
- Configure Claim Rule

Select the template for the claim rule that you want to create from the following list. The description provides details about each claim rule template.

Claim rule template:

Claim rule template description:

Using the Transform an Incoming Claim rule template you can select an incoming claim, change its claim type, and optionally change its claim value. For example, you can use this rule template to create a rule that will send a role claim with the same claim value of an incoming group claim. You can also use this rule to send a group claim with a claim value of "Purchasers" when there is an incoming group claim with a value of "Admins". Multiple claims with the same claim type may be emitted from this rule. Sources of incoming claims vary based on the rules being edited.

< Previous **Next >** Cancel

9. Ingrese el **Transform Account Name** (Nombre de la cuenta de transformación) y haga clic en **OK**.

Edit Rule - Transform Account Name



You can configure this rule to map an incoming claim type to an outgoing claim type. As an option, you can also map an incoming claim value to an outgoing claim value. Specify the incoming claim type to map to the outgoing claim type and whether the claim value should be mapped to a new claim value.

Claim rule name:

Transform Account Name

Rule template: Transform an Incoming Claim

Incoming claim type:

Windows account name

Incoming name ID format:

Unspecified

Outgoing claim type:

Name ID

Outgoing name ID format:

Transient Identifier

- ☒ Pass through all claim values
- ☐ Replace an incoming claim value with a different outgoing claim value

Incoming claim value:

Outgoing claim value:

Browse...

- ☐ Replace incoming e-mail suffix claims with a new e-mail suffix

New e-mail suffix:


Example: fabrikam.com

View Rule Language...

OK

Cancel


10. Haga clic en **Apply** (Aplicar) y luego en **OK** para confirmar.



Paso 5. Ajustando los Ajustes de Confianza


Asegúrese de que el **Secure hash algorithm** (Algoritmo de hash seguro) esté configurado en **SHA-256** en los ajustes de seguridad. Para hacer esto:

1. Abra el panel de control de AD FS. En la sección **Relying Party Trusts** (Partes confiables), haga clic con el botón derecho en el nombre y luego en **Properties** (Propiedades).




2. Vaya a la pestaña **Advanced** (Avanzado) y seleccione **SHA-256** en el campo **Secure hash algorithm** (Algoritmo de hash seguro).

3. Haga clic en .




Paso 6. Punto final Ajustes


1. Abra el panel de control de AD FS. En la sección **Relying Party Trusts** (Partes confiables), haga clic con el botón derecho en el nombre y luego en **Properties** (Propiedades).



2. En la pestaña **Endpoints** (Extremo), verifica el punto predeterminado:
 - Para el tipo de **Extremo** (Endpoints), seleccione **SAML Assertion Consumer**.
 - Para el tipo **Index** (Índice), seleccione **0**.
 - Para el tipo **Binding** (Enlace), seleccione **POST**.



- En el campo **Trusted URL** (URL confiable), introduzca una dirección como <https://youraccount.ispringlearn.com/module.php/saml/sp/saml2-acs.php/default-sp>. Deje en blanco el campo **Response URL** (URL de respuesta) y haga clic en **OK**.




3. Luego añade 2 puntos de cierre de sesión.

a. Para añadir un punto:


- Haga clic en **Add SAML** (Añadir SAML).
- Para el parámetro de tipo de **Endpoint** (Extremo), seleccione **SAML Assertion Consumer**.
- Para **Binding** (Enlace), seleccione **Artifact**.
- Para **Index** (Índice), seleccione 2.

- v. En el campo **Trusted URL** (URL confiable), introduzca una dirección como <https://youraccount.ispringlearn.com/module.php/saml/sp/saml2-acs.php/default-sp>.
- vi. Deje en blanco el campo **Response URL** (URL de respuesta) y haga clic en **OK**.




b. Añada un nuevo punto. Para hacer esto:

- i. Haga clic en **Add SAML** (Añadir SAML).
- ii. Para tipo de **Endpoint (Extremo)**, seleccione **SAML Logout**.
- iii. Para **Binding (Enlace)**, seleccione **POST**.
- iv. En el campo **Trusted URL** (URL confiable), introduzca una dirección como https://YOUR_ADFS_SERVERNAME/adfs/ls/?wa=wsignout1.0.
- v. Deje en blanco el **Response URL** (URL de respuesta) y haga clic en **OK**.



4. Asegúrese de que se hayan añadido los tres puntos finales. Haga clic en **Apply** (Aplicar) y luego en **OK** para confirmar.



The image shows the 'iSpring Learn SSO Properties' dialog box with the 'Endpoints' tab selected. The dialog has a title bar with a close button. Below the title bar are two rows of tabs: 'Monitoring', 'Identifiers', 'Encryption', 'Signature', 'Accepted Claims' in the first row, and 'Organization', 'Endpoints', 'Proxy Endpoints', 'Notes', 'Advanced' in the second row. The 'Endpoints' tab is active. Below the tabs is a text label: 'Specify the endpoints to use for SAML and WS-FederationPassive protocols.' Below this is a table with columns: 'URL', 'Index', 'Binding', 'Default', and 'Re'. The table is divided into two sections: 'SAML Assertion Consumer Endpoints' and 'SAML Logout Endpoints'. The 'SAML Assertion Consumer Endpoints' section contains two rows of data. The 'SAML Logout Endpoints' section contains one row of data. Below the table is a horizontal scrollbar. At the bottom of the dialog are three buttons: 'Add SAML...', 'Add WS-Federation...', and 'Remove'. At the very bottom are three buttons: 'OK', 'Cancel', and 'Apply'.

URL	Index	Binding	Default	Re
SAML Assertion Consumer Endpoints				
https://youraccount.ispringlea...	0	POST	No	
https://youraccount.ispringlea...	2	Artifact	No	
SAML Logout Endpoints				
https://YOUR_ADFS_SERV...		POST	No	

Paso 7. Verificar inicio de sesión único (SSO)

1. Vaya a su cuenta de iSpring LMS <https://youraccount.ispringlearn.com/>.
2. Haga clic en **Iniciar sesión con su cuenta corporativa**.

¡Bienvenido!

☒ Recordarme
 [¿Olvidó su contraseña?](#)

Iniciar sesión

Iniciar sesión con su cuenta corporativa

Se abrirá la cuenta personal del usuario.

Si se produce un error durante la configuración, envíe una captura de pantalla del error a support@ispring.es.

Correlación de campos de iSpring LMS y SSO

Además de las reglas, también puede especificar campos de **correlación** de iSpring LMS y atributos SSO: Nombre, Apellido, Puesto, Teléfono, etc. Saber más sobre la [correlación de campos de iSpring LMS y SSO](#).

En el lado de AD FS:

The screenshot shows the AD FS configuration interface. The left pane displays the 'Relying Party Trusts' list. The main pane shows the 'Edit Claim Issuance Policy for iSpring Learn SSO' dialog. The 'Issuance Transform Rules' section contains a table with the following data:

Order	Rule Name	Issued Claims
1	Attributes to iSpring Learn	email
2	Transform Account Name	Name ID

The right pane shows the 'Edit Rule - Attributes to iSpring Learn' dialog. The 'Claim rule name' is 'Attributes to iSpring Learn'. The 'Rule template' is 'Send LDAP Attributes as Claims'. The 'Attribute store' is 'Active Directory'. The 'Mapping of LDAP attributes to outgoing claim types' section contains a table with the following data:

LDAP Attribute (Select or type to add more)	Outgoing Claim Type (Select or type to add more)
E-Mail-Addresses	email
Given-Name	given_name
Surname	family_name
Title	job_title
Telephone-Number	phone

En el lado de iSpring LMS:

Asociar campos de iSpring LMS y atributos de SSO

Los atributos asociados se sincronizan automáticamente cuando un usuario inicia sesión.

Usuario	sub
Correo electrónico	email
Fecha de contratación	Escribir atributo
Las fechas deben enviarse en formato Unix Timestamp	
Nombre	given_name
Apellido	family_name

+ Añadir un campo

Autorización sin SAML

Si ha habilitado OpenID en su cuenta de iSpring LMS pero por alguna razón no puede iniciar sesión mediante inicio de sesión único, escriba la siguiente dirección web: https://yourcompany.ispringlearn.com/login?no_sso.

Ahora iniciarás sesión en la cuenta como de costumbre, utilizando tu usuario y contraseña.

Si obtiene un error 400 y un mensaje sobre que la solicitud se ha compuesto incorrectamente ("Cannot retrieve metadata for IdP '<https://myidp.com/oam/fed>' because it isn't a valid IdP for this SP") después de haber habilitado SAML en su cuenta de iSpring LMS, significa que el valor establecido para el **URL del emisor (ID de entidad del IdP)** campo es incorrecto.



Wrong Request

Cannot retrieve metadata for IdP 'https://myidp.com/oam/fed' because it isn't a valid IdP for this SP.

[← Go Back](#)

Para hacer que la autorización SAML funcione correctamente en su cuenta, copie la URL del texto de error y péguela en el campo **URL del Emisor (ID de Entidad IdP)**.

← Integración de Inicio de sesión único (SSO)

Ajustes SSO Accesos directos

SAML

JWT

OpenID

[¿Qué es esto?](#)

Activar

Ajustes de conexión

URL del emisor (ID de identidad del IdP):

URL de inicio de sesión único:

URL de cierre de sesión:

Huella digital del certificado:

☒ Redirigir a los usuarios a la página de Inicio de sesión SSO [?](#)